



* MAJOR UPGRADE * NETWORK LICENSE

License Information

Enclosed please find:

- "Network" CD containing:
 - ▶ Client installer of the latest release – ExtendSim 8
 - ▶ Server installer of the new License Manager
- "License Customization Files" CD containing a new site.tmp file to activate your license
- Network License Instructions

UPGRADING TO THE EXTENDSIM 8 NETWORK LICENSE

Note: You cannot install multiple ExtendSim License Managers on the same Server. Furthermore, because each Network License allows only a specified number of concurrent users, you are not allowed to have both Network Licenses (ExtendSim 7 and ExtendSim 8) installed for more than a short (up to 3 month) transition period.

Thus, you have two options when you install the ExtendSim 8 upgrade:

- 1 Uninstall the ExtendSim 7 files from the Server and Client computers.
Then install the ExtendSim 8 files. See the instructions for Option 1, below.
...Or...
- 2 Run the ExtendSim 7 and ExtendSim 8 Network Licenses on separate servers for up to 3 months.
Then uninstall the ExtendSim 7 files. See the instructions for Option 2, below.

Option 1: Uninstalling ExtendSim 7 before installing ExtendSim 8

- 1 Back up your ExtendSim 7 files.
- 2 Remove the ExtendSim 7 license from each Client computer:
 - Return any Client licenses that have been checked out.
(See "Checking In A License" on Page 3 of the Network License Instructions.)
 - On each Client, launch ExtendSim 7.
 - Give the command File > Network License > Remove License.
 - Use Windows' Add/Remove Programs to uninstall ExtendSim 7 from each Client. Keep the ExtendSim 7 folder until your custom models and libraries are moved to the ExtendSim 8 folder (see Step 4).
(To determine which non-checked out computers are currently using ExtendSim, go to the File > Network License > License Info command on any Client computer. To determine which computers have checked out licenses, look for recent "Checked out" log entries in the Server's WANExportLog.txt file.)
- 3 Next, remove the old License Manager from the Server:
 - In the ExtendSimServer folder on the Server, launch the application "Remove ExtendSim server.exe" – for Vista, right-click the file and select Run as Administrator; for others, double-click the file. You should get two messages: **License Successfully Removed** and **Service Successfully Removed**.
 - Use Windows' Add/Remove Programs on the Server to remove ExtendSim Server files.
 - Delete the ExtendSimServer folder from the Server.
- 4 Then, install the ExtendSim 8 Network License:
 - Follow the installation instructions on Page 2 of the Network License Instructions.
 - Install the new License Manager on the Server.
 - Install ExtendSim 8 on Client computers. Place any custom models and libraries from ExtendSim 7 into the appropriate ExtendSim 8 folder. (On Windows XP place in \My Documents\ExtendSim8 folder; Vista users place in \Documents\ExtendSim8.)

Option 2: Running the two network licenses in parallel, then uninstalling ExtendSim 7

Do not install the License Manager for ExtendSim 8 on the Server that has the License Manager for ExtendSim 7!

- 1 Install the ExtendSim 8 Network License:
 - Follow the installation instructions on Page 2 of the Network License Instructions.
 - Install the new License Manager on a different Server than the one that has the ExtendSim 7 License Manager; install ExtendSim 8 on Client computers.
- 2 Three months later, or earlier if you prefer, uninstall the ExtendSim 7 Network License:
 - Follow steps 1 and 2 for Option 1, above.
 - This removes the ExtendSim 7 license from Client computers, then from the Server.

Imagine That Inc. • 6830 Via Del Oro, Suite 230 • San Jose, CA 95119 USA
408.365.0305 • fax 408.629.1251 • sales@ExtendSim.com
www.ExtendSim.com

